Some Help With

Manage custom clients

TABLE OF CONTENT

Overview

Custom client (Build) types

Edit a custom client

- Editing a static build
- Editing a dynamic build

Delete a custom client


> **License:** Standard, Advanced, Ultimate-Cloud
>
> **Relevant for:** Admin, IT agents

This article provides an overview of how to modify or delete your custom client builds in my.anydesk II.

Overview

Once you've created a custom client, you can distribute it across multiple devices. A custom build may have several AnyDesk clients linked to it.

 © 2026 www.somehelpwith.com



If you need to adjust client settings, such as security configurations or feature access, you can apply changes through **my.anydesk II**.

> To modify individual clients in real time, see **this article**.

Custom client (Build) types

Changes to build can be applied in two ways, depending on the build type you selected during creation. There are two types of builds:

- **Static**- a custom build that requires reinstallation on all devices after each customization.
- **Dynamic**- a custom build that supports real-time updates across all linked clients without reinstallation. To use the *dynamic builds*, you need to Activate Central Management first.

Edit a custom client


You can adjust settings of already created and installed custom builds in my.anydesk II.

Editing a static build

After making changes to the static build, it should be reinstalled again on all devices.

To update a static build:

1. Sign in to my.anydesk II, go to **Builds** and select the build you want to modify.



2. On the opened page, click **Edit Build**.
3. Adjust the settings of the build and click **Save Build**.


> 🚨 **IMPORTANT**
>
> A *static build* cannot be changed to a *dynamic build* after creation.

Once updated, share the download link for reinstallation on all devices.

Editing a dynamic build

A dynamic build eliminates the need for manual client reinstallation unlike the static build. It streamlines the management process and ensures consistent updates across all clients.

> 💡 **NOTE**
>
> Ensure that **Central Management** is enabled under the **Security** section to confirm it is a dynamic build.




To update a dynamic build:


1. Sign in to [my.anydesk II] and in the **Activate Central Management** section, click **Provide Private Key**.

   > 💡 *To learn how to get your Private Key, see [What is a Private Key?]*

2. Paste the key and click **Continue**.




3. Go to **Builds**,select the build you want to edit, and then click **Edit Build**.




4. Apply the required changes and click **Save Build.**

Changes are applied automatically to all linked clients. You can also view:

- Devices where the build is installed



- The build's configuration history via **Options** > **Configuration History.**




Delete a custom client


If you created a build by accident or don't use the build anymore, you can permanently delete it.

There are two ways of how you can delete a build:

- Go to **Builds**, select the checkbox for the build you wish to delete and click **Delete**.



- Go to **Builds**, open the build, and click **Options** > **Delete Build**.



Once deleted, a custom build cannot be recovered.