Some Help With

Review and Create the AnyDesk Client - Finish Build Step

TABLE OF CONTENT

Video tutorial

General card

Download card

Security card


Create and the Builds list

MyAnyDesk in detail series

The **Finish Build** step is the last one in the my.anydesk.com Custom Client Generator: the complete configuration summary before creating the client. It’s your last chance to review everything — fixing afterwards means editing the build and (on Static builds) redeploying to every machine.

This guide explains **what each summary card reviews** and what happens after Create.

 © 2026 www.somehelpwith.com



Finish Build step with the complete summary

Video tutorial

This step explained on video:


> Watch video here

General card

The summary of step 1. Check especially:

- **Name** — how it will appear in your Builds list (search for it by this name later).
- **Client Type** — connection direction (*Incoming and outgoing connections* = Bi-Directional). Make sure it matches the machine's role.
- **OS** — platform and architecture (Windows 32-Bit, etc.).
- **Prefix** — the client identifier prefix.
- **Version** — the AnyDesk version that will be compiled.
- **File Name / Program Name** — the downloaded `.exe` and the installed name.
- **Address Book Access** — *Enabled* if the address book was left enabled.
- **License Bound** — the client is tied to your license.
- **Enable Session Requests** — *Disabled* if you chose the machine shouldn't start requests.
- **Enable Request Session Button** — the "request session" button in the client.

- **Address Book** — the book the machine will be added to on install (*None* if you didn't configure one).



General card of the summary

Real use case: if you expected the machine to register in the "HQ" address book and it says *None* here, go back with **Previous** to the General step and configure Add to Address Book — after Create it's too late for machines that already downloaded.

Download card


- **Download** — *Private* (only users with an account on your license) or *Public* (unique URL downloadable by anyone who has it).

Real use case: if you're going to publish the installer on your website for external customers, verify it says *Public*. If it stayed on *Private*, external customers won't be able to download it.

Security card

- **Preset Password** — preconfigured unattended access password (*Disabled* if you didn't set one).

- **Access Control** — *Disabled* if you didn't configure the ACL; otherwise it indicates only authorized IDs will be able to connect.
- **Proxy Server** — *Unset* or the chosen configuration.




Download and Security cards

Real use case: *Preset Password: Disabled* on a build meant for unattended access means nobody will get in without an interactive request — if your servers have no operator, go back and set the password under Permission Profiles.

Create and the Builds list

Clicking **Create** generates the build and it appears in the console's **Builds** section. Each row shows:

- **Build Name** and the badges: *Private/Public* (download type), *Bidirectional/Incoming/Outgoing* (connection type), *Static/Dynamic* (management), and the **creation date**.
- The icons on the right let you **download the installer** and **copy/manage** the build.



The new build in the Builds list

What comes after Create:

1. **Download** the installer from the list or share the link (if Public).
2. **Install** on a test machine before mass distribution.
3. If the build is **Dynamic**, any later edit propagates by itself; if it's **Static**, you'll have to redeploy.

MyAnyDesk in detail series

This guide is part of the series on the my.anydesk.com Custom Client Generator:

- Introduction - MyAnyDesk in detail
- Step 1 - General
- Step 2 - Security
- Step 3 - Visual
- Step 4 - Finish Build